

DNS Configuration

Use the F1 button on any page of a ThinManager wizard to launch Help for that page.

Visit <u>www.thinmanager.com/TechNotes/Intro/Manuals.shtml</u> to download the full Manual or the ThinManual.

Launch the **Domain Name Server Wizard** by selecting <u>Manage > DNS Configuration</u>. This will allow you to define the Domain Name Servers.

Oppomain Name Server Wizard	×
Domain Name Server Wizard Introduction	[©]тмз
The Domain Name Server Wizard defines the Name Server settings for your network.	
 System using a DNS server System without a DNS server 	
< <u>Back N</u> ext > Finish Cancel H	lelp

Domain Name Service Wizard - Introduction

The Domain Name Service Wizard Introduction screen allows the use of a DNS.

System without a DNS server - The default setting is for systems without a Domain Name Server.

System using a DNS server - This setting allows use of a DNS. Select the *Next* button to launch the *Domain Name Service Configuration* screen.



Domain Name Server Configuration Page

😇 Domain Name Serve	er Wizard 🛛 🗙
Domain Name Serv Enter the list of DM information.	Ver Configuration NS servers on your network and your domain
DNS Servers	
Duracia	Add DNS Server Remove DNS Server
Domain Search Domain	
	Read DNS Setting from this computer
< <u>B</u> ack <u>N</u> e	xt > Finish Cancel Help

Domain Name Server Configuration

The Domain Name Service Configuration page allows DNS settings to be configured.

Add DNS Server button will launch a dialog box that allows a DNS Server to be added to the list.

Remove DNS Server button will remove a highlighted DNS server from the list.

Up and *Down* arrow keys will change the order of DNS servers used. Highlight a DNS server in the list and select the appropriate arrow.

Domain is a field for the DNS domain name.

Search Domain will add the contents of the field as a prefix to any DNS searches.

Read DNS Setting from this computer will transfer the DNS settings from the current computer into ThinManager.

Add DNS Server button launches a DNS Server dialog box that allows the IP address of the DNS server to be entered.



DNS Server Entry Window

DNS Server	×
Name Server	OK)
255 . 255 . 255 . 255	Cancel

Domain Name Server Configuration - Add DNS Server

Name Server – This field selects a DNS for use in ThinManager when the IP address of a DNS is entered and the **OK** button is selected.

Additional IP addresses can be listed by selecting the *Add DNS Server* button *Domain Name Service Configuration* page again.

Select the *Finish* button when the DNS configuration is done.